



Installation Steps

V8.3

www.seqrite.com

Installing Seqrite Endpoint Protection server on Linux Operating System

To begin installation of Seqrite Endpoint Protection server, follow these steps:

1. Ensure that the product key is readily available and visit the following link:
<https://www.seqrite.com/seqrite-product-installer>

2. Enter the product key into the designated field and click **Submit**.

3. Select the desired option to download the installer based on your package specifications.

4. Save the installer to your preferred location on your Linux system.

5. Open the terminal on your Ubuntu endpoint and log in as a root user.

6. Execute the installer by typing the following command:

```
bash Seqrite_EndPoint_Security_8_3.sh
```

It prepares for the setup wizard to start.

7. The Installer Wizard screen appears. Click **Start**.

The license agreement appears. Read the License Agreement carefully. Installation and usage of Seqrite Endpoint Protection is subject to your formal acceptance of the Seqrite Endpoint Protection end-user license terms and conditions.

8. Press the **R** key to read more. Click **Yes, I Agree** on the Seqrite Endpoint Protection license agreement screen.

9. The Customer Information screen appears. Ensure that all the mandatory fields are populated with relevant information. Click **Next**.

10. The Installation Folder screen displays where the installation location is shown. Click **Next**.

11. Enter the IP Address of the machine on which you are installing the server. OR enter the Domain Name if you intend to execute the installation using a specific domain name.

If you need, you can provide the proxy server details for additional security. This is an optional step.

12. The Authentication screen appears. Provide the details here. Make a note of these details as you need the same credentials to log in to the console.

13. Click **Next** to proceed.

Verify the details on the Summary screen.

You can save the details as a text file by clicking **Save Summary**.

14. Click **Save**. The .txt file gets saved.

15. Click **Next**. The installation process starts.

It might take a few minutes to complete the installation.

16. Once all the components are ticked, the completion screen appears. Click **Finish**.

Now you need to activate the EPP central console to be able to manage/onboard the endpoints.

Steps to Activate the Console

1. For the console link, you can either use the ip address or the host name of your server machine.

For example, if you used the ip address while configuring the server, the link would be `https://<ipaddress>/eps/activate`.

2. Click **Activate**. OR

3. If you used the hostname while configuring the server, activate it using `https://<hostname>/eps/activate`. Enter the product key provided by the Seqrite team.

4. Click **Activate**.

5. A success message appears. Click **Login**.

6. It redirects you to the console login page. Enter the details you provided during registration. Click **Sign In**.

It takes you to the dashboard. Refer the [help](#) for more information.